


Microsoft Outlook 2003 Setup


This tutorial shows you how to set up Microsoft Outlook 2003 to work with your e-mail account. You can set up previous versions of Microsoft Outlook by using the settings in this tutorial.

To Set Up Your E-mail Account in Microsoft Outlook


1. In Microsoft Outlook, from the **E-mail Accounts** menu, select **Tools**.



2. On the E-mail Accounts wizard window, select **Add a new e-mail account**, and then click **Next**.



3. For your server type, select **POP3** or **IMAP**, and then click Next.





VALUE TECHNOLOGIES PAKISTAN

4. On the Internet E-mail Settings (POP3) window, enter your information as follows:

Your Name

- Your first and last name.

E-mail Address

- Your email address.

User Name

- Your email address, again.

Password

- Your email account password.

Incoming mail server (POP3)

- pop.*yourdomain*

Outgoing mail server (SMTP)

- smtp.*yourdomain*

(Note: See your order confirmation letter for pop & smtp server.)

E-mail Accounts


Internet E-mail Settings (POP3)
Each of these settings are required to get your e-mail account working.

User Information	Server Information
Your Name: <input type="text" value="Noman Ahmed"/>	Incoming mail server (POP3): <input type="text" value="mail.abc.com"/>
E-mail Address: <input type="text" value="noman@abc.com"/>	Outgoing mail server (SMTP): <input type="text" value="mail.abc.com"/>


Logon Information	Test Settings
User Name: <input type="text" value="noman@abc.com"/>	After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)
Password: <input type="password" value="*****"/>	
<input checked="" type="checkbox"/> Remember password	<input type="button" value="Test Account Settings ..."/>
<input type="checkbox"/> Log on using Secure Password Authentication (SPA)	<input type="button" value="More Settings ..."/>

< Back Next > Cancel


5. Click **More Settings**.
6. On the **Internet E-mail Settings** window, go to the **Outgoing Server** tab.
7. Make sure, ***My outgoing server (SMTP) requires authentication***, should be checked as below.



8. Go to the **Advanced** tab, and then change the settings as below.



9. Click **OK**.
10. Click **Next**.



E-mail Accounts [Close]

Internet E-mail Settings (POP3)
Each of these settings are required to get your e-mail account working.

User Information

Your Name:
E-mail Address:

Server Information

Incoming mail server (POP3):
Outgoing mail server (SMTP):

Logon Information

User Name:
Password:
 Remember password

Log on using Secure Password Authentication (SPA)

Test Settings

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

11. Click **Finish**.

