



VALUE TECHNOLOGIES PAKISTAN




Setting up Email on Outlook® 2010

Screen-by-Screen



VALUE TECHNOLOGIES PAKISTAN



Step 1

Open Microsoft Outlook 2010. Click File, and then click Add Account.



VALUE TECHNOLOGIES PAKISTAN

Add New Account

Auto Account Setup
Connect to other server types.

E-mail Account

Your Name:
Example: Ellen Adams

E-mail Address:
Example: ellen@contoso.com

Password:

Retype Password:
Type the password your Internet service provider has given you.

Text Messaging (SMS)

Manually configure server settings or additional server types


< Back Next > Cancel

Step 2

At the bottom, select Manually configure server settings or additional server types, and click Next.



VALUE TECHNOLOGIES PAKISTAN



Step 3

Select Internet E-mail, and click Next.



VALUE TECHNOLOGIES PAKISTAN

Add New Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information

Your Name:

E-mail Address:

Server Information

Account Type:

Incoming mail server:

Outgoing mail server (SMTP):

Logon Information

User Name:

Password:

Remember password

Require logon using Secure Password Authentication (SPA)

Test Account Settings

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings by clicking the Next button

Deliver new messages to:

New Outlook Data File

Existing Outlook Data File

< Back Next > Cancel

Step 4

Enter Your Name and full E-mail Address.



Add New Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information
Your Name: jolly Jones
E-mail Address: jolly@coolexample.com

Server Information
Account Type: POP3
Incoming mail server: pop.secureserver.net
Outgoing mail server (SMTP): smtpout.secureserver.net

Logon Information
User Name: jolly@coolexample.com
Password: *****
 Remember password
 Require logon using Secure Password Authentication (SPA)

Test Account Settings
After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)
Test Account Settings ...
 Test Account Settings by clicking the Next button

Deliver new messages to:
 New Outlook Data File
 Existing Outlook Data File
Browse

More Settings ...

< Back Next > Cancel

Step 5

Account Type: POP3

Incoming Mail server: mail.domainname.xyz

Outgoing Mail server: mail.domainname.xyz

User Name: the full email address

Password: the password for the email address

Note: See your order confirmation letter for pop & smtp server



VALUE TECHNOLOGIES PAKISTAN

Add New Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information
Your Name:
E-mail Address:

Server Information
Account Type:
Incoming mail server:
Outgoing mail server (SMTP):

Logon Information
User Name:
Password:
 Remember password
 Require logon using Secure Password Authentication (SPA)

Test Account Settings
After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

 Test Account Settings by clicking the Next button

Deliver new messages to:
 New Outlook Data File
 Existing Outlook Data File

Step 6

Enter your User Name (your full email address) and Password, and select Remember password.



VALUE TECHNOLOGIES PAKISTAN

Add New Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information
Your Name:
E-mail Address:

Server Information
Account Type:
Incoming mail server:
Outgoing mail server (SMTP):

Logon Information
User Name:
Password:
 Remember password
 Require logon using Secure Password Authentication (SPA)

Test Account Settings
After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

 Test Account Settings by clicking the Next button


Deliver new messages to:
 New Outlook Data File
 Existing Outlook Data File

< Back Next > Cancel




Step 7

Click More Settings.



Step 8

Make sure, *My outgoing server (SMTP) requires authentication*, should be checked



Step 9

Go to the **Advanced** tab, and then change the settings as above.



VALUE TECHNOLOGIES PAKISTAN

Add New Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information
Your Name:
E-mail Address:

Server Information
Account Type:
Incoming mail server:
Outgoing mail server (SMTP):

Logon Information
User Name:
Password:
 Remember password
 Require logon using Secure Password Authentication (SPA)

Test Account Settings
After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)


 Test Account Settings by clicking the Next button

Deliver new messages to:
 New Outlook Data File
 Existing Outlook Data File

< Back Next > Cancel

Step 10

Click Next.




Step 11

Outlook 2010 will test your settings. When it's done, click Close.



VALUE TECHNOLOGIES PAKISTAN



Step 12

Click Finish.



VALUE TECHNOLOGIES PAKISTAN

That's it.

That's it. If everything is working OK, you should see some email messages. If you don't, press the F9 key on your computer to receive messages.